

---

# **python-neutronclient Documentation**

*Release 11.3.2.dev2*

**Neutron Contributors**

**Sep 06, 2024**



# CONTENTS

<b>1</b>	<b>User Documentation</b>	<b>3</b>
1.1	Using CLI	3
1.1.1	OpenStackClient	3
	Advanced Network Commands in OpenStack Client	3
	BGP Dynamic Routing	3
	bgp speaker create	3
	bgp speaker delete	5
	bgp speaker list	5
	bgp speaker set	6
	bgp speaker show	7
	bgp speaker add network	8
	bgp speaker remove network	8
	bgp speaker add peer	8
	bgp speaker remove peer	8
	bgp speaker list advertised routes	9
	bgp peer create	10
	bgp peer delete	11
	bgp peer list	11
	bgp peer set	12
	bgp peer show	13
	bgp dragent add speaker	13
	bgp dragent list	14
	bgp dragent remove speaker	15
	firewall group	15
	firewall group create	15
	firewall group delete	17
	firewall group list	17
	firewall group set	18
	firewall group show	19
	firewall group unset	20
	firewall group policy	21
	firewall group policy add rule	21
	firewall group policy create	21
	firewall group policy delete	23
	firewall group policy list	23
	firewall group policy remove rule	24
	firewall group policy set	24
	firewall group policy show	25
	firewall group policy unset	26

firewall group rule . . . . .	27
firewall group rule create . . . . .	27
firewall group rule delete . . . . .	29
firewall group rule list . . . . .	29
firewall group rule set . . . . .	30
firewall group rule show . . . . .	32
firewall group rule unset . . . . .	33
network log . . . . .	34
network loggable resources list . . . . .	34
network log create . . . . .	35
network log delete . . . . .	37
network log list . . . . .	37
network log set . . . . .	38
network log show . . . . .	38
bgpvpn . . . . .	39
bgpvpn create . . . . .	39
bgpvpn delete . . . . .	41
bgpvpn list . . . . .	41
bgpvpn set . . . . .	42
bgpvpn show . . . . .	43
bgpvpn unset . . . . .	44
bgpvpn network association create . . . . .	45
bgpvpn network association delete . . . . .	46
bgpvpn network association list . . . . .	47
bgpvpn network association show . . . . .	48
bgpvpn router association create . . . . .	49
bgpvpn router association delete . . . . .	50
bgpvpn router association list . . . . .	50
bgpvpn router association set . . . . .	52
bgpvpn router association show . . . . .	52
bgpvpn router association unset . . . . .	53
bgpvpn port association create . . . . .	54
bgpvpn port association delete . . . . .	55
bgpvpn port association list . . . . .	55
bgpvpn port association set . . . . .	57
bgpvpn port association show . . . . .	57
bgpvpn port association unset . . . . .	58
networking sfc . . . . .	59
sfc flow classifier create . . . . .	59
sfc flow classifier delete . . . . .	61
sfc flow classifier list . . . . .	61
sfc flow classifier set . . . . .	62
sfc flow classifier show . . . . .	63
sfc port chain create . . . . .	63
sfc port chain delete . . . . .	65
sfc port chain list . . . . .	65
sfc port chain set . . . . .	66
sfc port chain show . . . . .	67
sfc port chain unset . . . . .	67
sfc port pair create . . . . .	68
sfc port pair delete . . . . .	69

sfc port pair list . . . . .	69
sfc port pair set . . . . .	70
sfc port pair show . . . . .	71
sfc port pair group create . . . . .	72
sfc port pair group delete . . . . .	73
sfc port pair group list . . . . .	73
sfc port pair group set . . . . .	74
sfc port pair group show . . . . .	75
sfc port pair group unset . . . . .	75
sfc service graph create . . . . .	76
sfc service graph delete . . . . .	77
sfc service graph list . . . . .	77
sfc service graph set . . . . .	78
sfc service graph show . . . . .	78
network onboard subnets . . . . .	79
network onboard subnets . . . . .	79
VPN Endpoint Group . . . . .	80
vpn endpoint group create . . . . .	80
vpn endpoint group delete . . . . .	81
vpn endpoint group list . . . . .	81
vpn endpoint group set . . . . .	82
vpn endpoint group show . . . . .	83
VPN IKE Policy . . . . .	84
vpn ike policy create . . . . .	84
vpn ike policy delete . . . . .	85
vpn ike policy list . . . . .	85
vpn ike policy set . . . . .	87
vpn ike policy show . . . . .	87
VPN IPsec Policy . . . . .	88
vpn ipsec policy create . . . . .	88
vpn ipsec policy delete . . . . .	90
vpn ipsec policy list . . . . .	90
vpn ipsec policy set . . . . .	91
vpn ipsec policy show . . . . .	92
VPN IPsec Site Connection . . . . .	93
vpn ipsec site connection create . . . . .	93
vpn ipsec site connection delete . . . . .	95
vpn ipsec site connection list . . . . .	95
vpn ipsec site connection set . . . . .	96
vpn ipsec site connection show . . . . .	98
VPN Service . . . . .	98
vpn service create . . . . .	99
vpn service delete . . . . .	100
vpn service list . . . . .	100
vpn service set . . . . .	101
vpn service show . . . . .	102
1.1.2 neutron CLI . . . . .	103
1.2 neutronclient Python API . . . . .	103
1.2.1 Basic Usage . . . . .	103

**2 Contributor Guide 105**

2.1	Contributor Guide . . . . .	105
2.1.1	Transition to OpenStack Client . . . . .	105
	Overview . . . . .	105
	Transition Steps . . . . .	106
	Developer Guide . . . . .	107
	Developer References . . . . .	108
<b>3</b>	<b>History</b>	<b>109</b>

This is a client for OpenStack Networking API. It provides *Python API bindings* (the neutronclient module).

There is [OpenStack Client \(OSC\)](#). CLI which support the Networking API.





## USER DOCUMENTATION

### 1.1 Using CLI

There is `OpenStackClient` (OSC) which support the Networking API

#### 1.1.1 OpenStackClient

`OpenStackClient` provides the basic network commands and `python-neutronclient` provides *extensions* (aka OSC plugins) for advanced networking services.

#### Advanced Network Commands in OpenStack Client

The following list covers the extended commands for advanced network services available in `openstack` command.

These commands can be referenced by doing `openstack help` and the detail of individual command can be referred by `openstack help <command-name>`.

#### BGP Dynamic Routing

BGP dynamic routing enables announcement of project subnet prefixes via BGP. Admins create BGP speakers and BGP peers. BGP peers can be associated with BGP speakers, thereby enabling peering sessions with operator infrastructure. BGP speakers can be associated with networks, which controls which routes are announced to peers.

Network v2

#### `bgp speaker create`

Create a BGP speaker

```
openstack bgp speaker create
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
```

(continues on next page)

(continued from previous page)

```
[--fit-width]
[--print-empty]
--local-as <local-as>
[--ip-version {4,6}]
[--advertise-floating-ip-host-routes]
[--no-advertise-floating-ip-host-routes]
[--advertise-tenant-networks]
[--no-advertise-tenant-networks]
[--project <project>]
[--project-domain <project-domain>]
<name>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--local-as** <local-as>

Local AS number. (Integer in [1, 4294967295] is allowed.)

**--ip-version** <IP\_VERSION>

IP version for the BGP speaker (default is 4)

**--advertise-floating-ip-host-routes**

Enable the advertisement of floating IP host routes by the BGP speaker. (default)

**--no-advertise-floating-ip-host-routes**

Disable the advertisement of floating IP host routes by the BGP speaker.

**--advertise-tenant-networks**

Enable the advertisement of tenant network routes by the BGP speaker. (default)

**--no-advertise-tenant-networks**

Disable the advertisement of tenant network routes by the BGP speaker.

**--project** <project>

Owners project (name or ID)

**--project-domain** <project-domain>

Domain the project belongs to (name or ID). This can be used in case collisions between project names exist.

**name**

Name of the BGP speaker to create

This command is provided by the python-neutronclient plugin.

## bgp speaker delete

Delete a BGP speaker

```
openstack bgp speaker delete <bgp-speaker>
```

**bgp-speaker**

BGP speaker to delete (name or ID)

This command is provided by the python-neutronclient plugin.

## bgp speaker list

List BGP speakers

```
openstack bgp speaker list
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
  [--noindent]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--sort-column SORT_COLUMN]
  [--sort-ascending | --sort-descending]
  [--agent <agent-id>]
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--quote** <QUOTE\_MODE>

when to include quotes, defaults to nonnumeric

**--noindent**

whether to disable indenting the JSON

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--sort-column** SORT\_COLUMN

specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated

**--sort-ascending**

sort the column(s) in ascending order

**--sort-descending**

sort the column(s) in descending order

**--agent** <agent-id>

List BGP speakers hosted by an agent (ID only)

This command is provided by the python-neutronclient plugin.

## bgp speaker set

Set BGP speaker properties

```
openstack bgp speaker set
  [--name NAME]
  [--advertise-floating-ip-host-routes]
  [--no-advertise-floating-ip-host-routes]
  [--advertise-tenant-networks]
  [--no-advertise-tenant-networks]
  <bgp-speaker>
```

**--name** <NAME>

New name for the BGP speaker

**--advertise-floating-ip-host-routes**

Enable the advertisement of floating IP host routes by the BGP speaker. (default)

**--no-advertise-floating-ip-host-routes**

Disable the advertisement of floating IP host routes by the BGP speaker.

**--advertise-tenant-networks**

Enable the advertisement of tenant network routes by the BGP speaker. (default)

**--no-advertise-tenant-networks**

Disable the advertisement of tenant network routes by the BGP speaker.

**bgp-speaker**

BGP speaker to update (name or ID)

This command is provided by the python-neutronclient plugin.

**bgp speaker show**

Show a BGP speaker

```
openstack bgp speaker show
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  <bgp-speaker>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**bgp-speaker**

BGP speaker to display (name or ID)

This command is provided by the python-neutronclient plugin.

### bgp speaker add network

Add a network to a BGP speaker

```
openstack bgp speaker add network <bgp-speaker> <network>
```

#### **bgp-speaker**

BGP speaker (name or ID)

#### **network**

Network to add (name or ID)

This command is provided by the python-neutronclient plugin.

### bgp speaker remove network

Remove a network from a BGP speaker

```
openstack bgp speaker remove network <bgp-speaker> <network>
```

#### **bgp-speaker**

BGP speaker (name or ID)

#### **network**

Network to remove (name or ID)

This command is provided by the python-neutronclient plugin.

### bgp speaker add peer

Add a peer to a BGP speaker

```
openstack bgp speaker add peer <bgp-speaker> <bgp-peer>
```

#### **bgp-speaker**

BGP speaker (name or ID)

#### **bgp-peer**

BGP Peer to add (name or ID)

This command is provided by the python-neutronclient plugin.

### bgp speaker remove peer

Remove a peer from a BGP speaker

```
openstack bgp speaker remove peer <bgp-speaker> <bgp-peer>
```

#### **bgp-speaker**

BGP speaker (name or ID)

**bgp-peer**

BGP Peer to remove (name or ID)

This command is provided by the python-neutronclient plugin.

**bgp speaker list advertised routes**

List routes advertised

```
openstack bgp speaker list advertised routes
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
  [--noindent]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--sort-column SORT_COLUMN]
  [--sort-ascending | --sort-descending]
  <bgp-speaker>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--quote** <QUOTE\_MODE>

when to include quotes, defaults to nonnumeric

**--noindent**

whether to disable indenting the JSON

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--sort-column** SORT\_COLUMN

specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated

**--sort-ascending**

sort the column(s) in ascending order

**--sort-descending**

sort the column(s) in descending order

**bgp-speaker**

BGP speaker (name or ID)

This command is provided by the python-neutronclient plugin.

**bgp peer create**

Create a BGP peer

```
openstack bgp peer create
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  --peer-ip <peer-ip-address>
  --remote-as <peer-remote-as>
  [--auth-type <peer-auth-type>]
  [--password <auth-password>]
  [--project <project>]
  [--project-domain <project-domain>]
  <name>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--peer-ip** <peer-ip-address>

Peer IP address

**--remote-as** <peer-remote-as>

Peer AS number. (Integer in [1, 4294967295] is allowed)



**--auth-type** <peer-auth-type>

Authentication algorithm. Supported algorithms: none (default), md5

**--password** <auth-password>

Authentication password

**--project** <project>

Owners project (name or ID)

**--project-domain** <project-domain>

Domain the project belongs to (name or ID). This can be used in case collisions between project names exist.

**name**

Name of the BGP peer to create

This command is provided by the python-neutronclient plugin.

### bgp peer delete

Delete a BGP peer

```
openstack bgp peer delete <bgp-peer>
```

**bgp-peer**

BGP peer to delete (name or ID)

This command is provided by the python-neutronclient plugin.

### bgp peer list

List BGP peers

```
openstack bgp peer list
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
  [--noindent]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--sort-column SORT_COLUMN]
  [--sort-ascending | --sort-descending]
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--quote** <QUOTE\_MODE>

when to include quotes, defaults to nonnumeric

**--noindent**

whether to disable indenting the JSON

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--sort-column** SORT\_COLUMN

specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated

**--sort-ascending**

sort the column(s) in ascending order

**--sort-descending**

sort the column(s) in descending order

This command is provided by the python-neutronclient plugin.

## bgp peer set

Update a BGP peer

```
openstack bgp peer set
  [--name NAME]
  [--password <auth-password>]
  <bgp-peer>
```

**--name** <NAME>

Updated name of the BGP peer

**--password** <auth-password>

Updated authentication password

**bgp-peer**

BGP peer to update (name or ID)

This command is provided by the python-neutronclient plugin.

## bgp peer show

Show information for a BGP peer

```

openstack bgp peer show
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  <bgp-peer>

```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**bgp-peer**

BGP peer to display (name or ID)

This command is provided by the python-neutronclient plugin.

## bgp dragent add speaker

Add a BGP speaker to a dynamic routing agent

```

openstack bgp dragent add speaker <agent-id> <bgp-speaker>

```

**agent-id**

ID of the dynamic routing agent

### bgp-speaker

ID or name of the BGP speaker

This command is provided by the python-neutronclient plugin.

### bgp dragent list

List dynamic routing agents

```
openstack bgp dragent list
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
  [--noindent]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--sort-column SORT_COLUMN]
  [--sort-ascending | --sort-descending]
  [--bgp-speaker <bgp-speaker>]
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--quote** <QUOTE\_MODE>

when to include quotes, defaults to nonnumeric

**--noindent**

whether to disable indenting the JSON

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--sort-column** SORT\_COLUMN

specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated

**--sort-ascending**

sort the column(s) in ascending order

**--sort-descending**

sort the column(s) in descending order

**--bgp-speaker** <bgp-speaker>

List dynamic routing agents hosting a BGP speaker (name or ID)

This command is provided by the python-neutronclient plugin.

### bgp dragent remove speaker

Removes a BGP speaker from a dynamic routing agent

```
openstack bgp dragent remove speaker <agent-id> <bgp-speaker>
```

**agent-id**

ID of the dynamic routing agent

**bgp-speaker**

ID or name of the BGP speaker

This command is provided by the python-neutronclient plugin.

### firewall group

A **firewall group** is a perimeter firewall management to Networking. Firewall group uses iptables to apply firewall policy to all VM ports and router ports within a project.

Network v2

### firewall group create

Create a new firewall group

```
openstack firewall group create
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--name NAME]
  [--description <description>]
  [--ingress-firewall-policy <ingress-firewall-policy> | --no-ingress-
↪firewall-policy]
  [--egress-firewall-policy <egress-firewall-policy> | --no-egress-firewall-
↪policy]
  [--share | --no-share]
  [--enable | --disable]
  [--project <project>]
  [--project-domain <project-domain>]
  [--port <port> | --no-port]
```

- f** <FORMATTER>, **--format** <FORMATTER>  
the output format, defaults to table
- c** COLUMN, **--column** COLUMN  
specify the column(s) to include, can be repeated to show multiple columns
- noindent**  
whether to disable indenting the JSON
- prefix** <PREFIX>  
add a prefix to all variable names
- max-width** <integer>  
Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.
- fit-width**  
Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable
- print-empty**  
Print empty table if there is no data to show.
- name** <NAME>  
Name for the firewall group
- description** <description>  
Description of the firewall group
- ingress-firewall-policy** <ingress-firewall-policy>  
Ingress firewall policy (name or ID)
- no-ingress-firewall-policy**  
Detach ingress firewall policy from the firewall group
- egress-firewall-policy** <egress-firewall-policy>  
Egress firewall policy (name or ID)
- no-egress-firewall-policy**  
Detach egress firewall policy from the firewall group
- share**  
Share the firewall group to be used in all projects (by default, it is restricted to be used by the current project).
- no-share**  
Restrict use of the firewall group to the current project
- enable**  
Enable firewall group
- disable**  
Disable firewall group
- project** <project>  
Owners project (name or ID)

**--project-domain** <project-domain>

Domain the project belongs to (name or ID). This can be used in case collisions between project names exist.

**--port** <port>

Port(s) (name or ID) to apply firewall group. This option can be repeated

**--no-port**

Detach all port from the firewall group

This command is provided by the python-neutronclient plugin.

## firewall group delete

Delete firewall group(s)

```
openstack firewall group delete <firewall-group> [<firewall-group> ...]
```

**firewall-group**

Firewall group(s) to delete (name or ID)

This command is provided by the python-neutronclient plugin.

## firewall group list

List firewall groups

```
openstack firewall group list
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
  [--noindent]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--sort-column SORT_COLUMN]
  [--sort-ascending | --sort-descending]
  [--long]
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--quote** <QUOTE\_MODE>

when to include quotes, defaults to nonnumeric

**--noindent**

whether to disable indenting the JSON

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--sort-column** SORT\_COLUMN

specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated

**--sort-ascending**

sort the column(s) in ascending order

**--sort-descending**

sort the column(s) in descending order

**--long**

List additional fields in output

This command is provided by the python-neutronclient plugin.

## firewall group set

Set firewall group properties

```
openstack firewall group set
  [--name NAME]
  [--description <description>]
  [--ingress-firewall-policy <ingress-firewall-policy> | --no-ingress-
↪firewall-policy]
  [--egress-firewall-policy <egress-firewall-policy> | --no-egress-firewall-
↪policy]
  [--share | --no-share]
  [--enable | --disable]
  [--port <port>]
  [--no-port]
  <firewall-group>
```

**--name** <NAME>

Name for the firewall group

**--description** <description>

Description of the firewall group

**--ingress-firewall-policy** <ingress-firewall-policy>

Ingress firewall policy (name or ID)



**--no-ingress-firewall-policy**

Detach ingress firewall policy from the firewall group

**--egress-firewall-policy** <egress-firewall-policy>

Egress firewall policy (name or ID)

**--no-egress-firewall-policy**

Detach egress firewall policy from the firewall group

**--share**

Share the firewall group to be used in all projects (by default, it is restricted to be used by the current project).

**--no-share**

Restrict use of the firewall group to the current project

**--enable**

Enable firewall group

**--disable**

Disable firewall group

**--port** <port>

Port(s) (name or ID) to apply firewall group. This option can be repeated

**--no-port**

Detach all port from the firewall group

**firewall-group**

Firewall group to update (name or ID)

This command is provided by the python-neutronclient plugin.

**firewall group show**

Display firewall group details

```
openstack firewall group show
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  <firewall-group>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**firewall-group**

Firewall group to show (name or ID)

This command is provided by the python-neutronclient plugin.

## firewall group unset

Unset firewall group properties

```
openstack firewall group unset
  [--port <port> | --all-port]
  [--ingress-firewall-policy]
  [--egress-firewall-policy]
  [--share]
  [--enable]
  <firewall-group>
```

**--port** <port>

Port(s) (name or ID) to apply firewall group. This option can be repeated

**--all-port**

Remove all ports for this firewall group

**--ingress-firewall-policy**

Ingress firewall policy (name or ID) to delete

**--egress-firewall-policy**

Egress firewall policy (name or ID) to delete

**--share**

Restrict use of the firewall group to the current project

**--enable**

Disable firewall group

**firewall-group**

Firewall group to unset (name or ID)

This command is provided by the python-neutronclient plugin.

**firewall group policy**

A **firewall group policy** is an ordered collection of firewall rules. A firewall policy can be shared across projects. Thus it can also be made part of an audit workflow wherein the `firewall_policy` can be audited by the relevant entity that is authorized (and can be different from the projects which create or use the firewall group policy).

Network v2

**firewall group policy add rule**

Insert a rule into a given firewall policy

```
openstack firewall group policy add rule
  [--insert-before <firewall-rule>]
  [--insert-after <firewall-rule>]
  <firewall-policy>
  <firewall-rule>
```

**--insert-before** <firewall-rule>

Insert the new rule before this existing rule (name or ID)

**--insert-after** <firewall-rule>

Insert the new rule after this existing rule (name or ID)

**firewall-policy**

Firewall policy to insert rule (name or ID)

**firewall-rule**

Firewall rule to be inserted (name or ID)

This command is provided by the python-neutronclient plugin.

**firewall group policy create**

Create a new firewall policy

```
openstack firewall group policy create
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
```

(continues on next page)

(continued from previous page)

```
[--description DESCRIPTION]
[--audited | --no-audited]
[--share | --no-share]
[--project <project>]
[--project-domain <project-domain>]
[--firewall-rule <firewall-rule> | --no-firewall-rule]
<name>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--description** <DESCRIPTION>

Description of the firewall policy

**--audited**

Enable auditing for the policy

**--no-audited**

Disable auditing for the policy

**--share**

Share the firewall policy to be used in all projects (by default, it is restricted to be used by the current project).

**--no-share**

Restrict use of the firewall policy to the current project

**--project** <project>

Owners project (name or ID)

**--project-domain** <project-domain>

Domain the project belongs to (name or ID). This can be used in case collisions between project names exist.

**--firewall-rule** <firewall-rule>  
 Firewall rule(s) to apply (name or ID)

**--no-firewall-rule**  
 Unset all firewall rules from firewall policy

**name**  
 Name for the firewall policy

This command is provided by the python-neutronclient plugin.

### firewall group policy delete

Delete firewall policy(s)

```
openstack firewall group policy delete
  <firewall-policy>
  [<firewall-policy> ...]
```

**firewall-policy**  
 Firewall policy(s) to delete (name or ID)

This command is provided by the python-neutronclient plugin.

### firewall group policy list

List firewall policies

```
openstack firewall group policy list
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
  [--noindent]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--sort-column SORT_COLUMN]
  [--sort-ascending | --sort-descending]
  [--long]
```

**-f** <FORMATTER>, **--format** <FORMATTER>  
 the output format, defaults to table

**-c** COLUMN, **--column** COLUMN  
 specify the column(s) to include, can be repeated to show multiple columns

**--quote** <QUOTE\_MODE>  
 when to include quotes, defaults to nonnumeric

**--noindent**  
 whether to disable indenting the JSON

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--sort-column** SORT\_COLUMN

specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated

**--sort-ascending**

sort the column(s) in ascending order

**--sort-descending**

sort the column(s) in descending order

**--long**

List additional fields in output

This command is provided by the python-neutronclient plugin.

## firewall group policy remove rule

Remove a rule from a given firewall policy

```
openstack firewall group policy remove rule
  <firewall-policy>
  <firewall-rule>
```

**firewall-policy**

Firewall policy to remove rule (name or ID)

**firewall-rule**

Firewall rule to remove from policy (name or ID)

This command is provided by the python-neutronclient plugin.

## firewall group policy set

Set firewall policy properties

```
openstack firewall group policy set
  [--description DESCRIPTION]
  [--audited | --no-audited]
  [--share | --no-share]
  [--name <name>]
  [--firewall-rule <firewall-rule>]
```

(continues on next page)

(continued from previous page)

```
[--no-firewall-rule]
<firewall-policy>
```

**--description** <DESCRIPTION>

Description of the firewall policy

**--audited**

Enable auditing for the policy

**--no-audited**

Disable auditing for the policy

**--share**

Share the firewall policy to be used in all projects (by default, it is restricted to be used by the current project).

**--no-share**

Restrict use of the firewall policy to the current project

**--name** <name>

Name for the firewall policy

**--firewall-rule** <firewall-rule>

Firewall rule(s) to apply (name or ID)

**--no-firewall-rule**

Remove all firewall rules from firewall policy

**firewall-policy**

Firewall policy to update (name or ID)

This command is provided by the python-neutronclient plugin.

## firewall group policy show

Display firewall policy details

```
openstack firewall group policy show
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  <firewall-policy>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**firewall-policy**

Firewall policy to show (name or ID)

This command is provided by the python-neutronclient plugin.

### firewall group policy unset

Unset firewall policy properties

```
openstack firewall group policy unset
  [--firewall-rule <firewall-rule> | --all-firewall-rule]
  [--audited]
  [--share]
  <firewall-policy>
```

**--firewall-rule** <firewall-rule>

Remove firewall rule(s) from the firewall policy (name or ID)

**--all-firewall-rule**

Remove all firewall rules from the firewall policy

**--audited**

Disable auditing for the policy

**--share**

Restrict use of the firewall policy to the current project

**firewall-policy**

Firewall policy to unset (name or ID)

This command is provided by the python-neutronclient plugin.



## firewall group rule

A **firewall group rule** represents a collection of attributes like ports, IP addresses which define match criteria and action (allow, or deny) that needs to be taken on the matched data traffic.

Network v2

### firewall group rule create

Create a new firewall rule

```
openstack firewall group rule create
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--name <name>]
  [--description <description>]
  [--protocol {tcp,udp,icmp,any}]
  [--action {allow,deny,reject}]
  [--ip-version <ip-version>]
  [--source-ip-address <source-ip-address> | --no-source-ip-address]
  [--destination-ip-address <destination-ip-address> | --no-destination-ip-
↪address]
  [--source-port <source-port> | --no-source-port]
  [--destination-port <destination-port> | --no-destination-port]
  [--share | --no-share]
  [--enable-rule | --disable-rule]
  [--source-firewall-group <source-firewall-group> | --no-source-firewall-
↪group]
  [--destination-firewall-group <destination-firewall-group> | --no-
↪destination-firewall-group]
  [--project <project>]
  [--project-domain <project-domain>]
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--name** <name>

Name of the firewall rule

**--description** <description>

Description of the firewall rule

**--protocol** <PROTOCOL>

Protocol for the firewall rule

**--action** <ACTION>

Action for the firewall rule

**--ip-version** <ip-version>

Set IP version 4 or 6 (default is 4)

**--source-ip-address** <source-ip-address>

Source IP address or subnet

**--no-source-ip-address**

Detach source IP address

**--destination-ip-address** <destination-ip-address>

Destination IP address or subnet

**--no-destination-ip-address**

Detach destination IP address

**--source-port** <source-port>

Source port number or range(integer in [1, 65535] or range like 123:456)

**--no-source-port**

Detach source port number or range

**--destination-port** <destination-port>

Destination port number or range(integer in [1, 65535] or range like 123:456)

**--no-destination-port**

Detach destination port number or range

**--share**

Share the firewall rule to be used in all projects (by default, it is restricted to be used by the current project).

**--no-share**

Restrict use of the firewall rule to the current project

**--enable-rule**

Enable this rule (default is enabled)

**--disable-rule**

Disable this rule

**--source-firewall-group** <source-firewall-group>

Source firewall group (name or ID)

**--no-source-firewall-group**

No associated destination firewall group

**--destination-firewall-group** <destination-firewall-group>

Destination firewall group (name or ID)

**--no-destination-firewall-group**

No associated destination firewall group

**--project** <project>

Owners project (name or ID)

**--project-domain** <project-domain>

Domain the project belongs to (name or ID). This can be used in case collisions between project names exist.

This command is provided by the python-neutronclient plugin.

**firewall group rule delete**

Delete firewall rule(s)

```
openstack firewall group rule delete
  <firewall-rule>
  [<firewall-rule> ...]
```

**firewall-rule**

Firewall rule(s) to delete (name or ID)

This command is provided by the python-neutronclient plugin.

**firewall group rule list**

List firewall rules that belong to a given tenant

```
openstack firewall group rule list
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
  [--noindent]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
```

(continues on next page)

(continued from previous page)

```
[--sort-column SORT_COLUMN]
[--sort-ascending | --sort-descending]
[--long]
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--quote** <QUOTE\_MODE>

when to include quotes, defaults to nonnumeric

**--noindent**

whether to disable indenting the JSON

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--sort-column** SORT\_COLUMN

specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated

**--sort-ascending**

sort the column(s) in ascending order

**--sort-descending**

sort the column(s) in descending order

**--long**

List additional fields in output

This command is provided by the python-neutronclient plugin.

## firewall group rule set

Set firewall rule properties

```
openstack firewall group rule set
  [--name <name>]
  [--description <description>]
  [--protocol {tcp,udp,icmp,any}]
  [--action {allow,deny,reject}]
  [--ip-version <ip-version>]
```

(continues on next page)

(continued from previous page)

```

[--source-ip-address <source-ip-address> | --no-source-ip-address]
[--destination-ip-address <destination-ip-address> | --no-destination-ip-
↪address]
[--source-port <source-port> | --no-source-port]
[--destination-port <destination-port> | --no-destination-port]
[--share | --no-share]
[--enable-rule | --disable-rule]
[--source-firewall-group <source-firewall-group> | --no-source-firewall-
↪group]
[--destination-firewall-group <destination-firewall-group> | --no-
↪destination-firewall-group]
<firewall-rule>

```

**--name** <name>

Name of the firewall rule

**--description** <description>

Description of the firewall rule

**--protocol** <PROTOCOL>

Protocol for the firewall rule

**--action** <ACTION>

Action for the firewall rule

**--ip-version** <ip-version>

Set IP version 4 or 6 (default is 4)

**--source-ip-address** <source-ip-address>

Source IP address or subnet

**--no-source-ip-address**

Detach source IP address

**--destination-ip-address** <destination-ip-address>

Destination IP address or subnet

**--no-destination-ip-address**

Detach destination IP address

**--source-port** <source-port>

Source port number or range(integer in [1, 65535] or range like 123:456)

**--no-source-port**

Detach source port number or range

**--destination-port** <destination-port>

Destination port number or range(integer in [1, 65535] or range like 123:456)

**--no-destination-port**

Detach destination port number or range

**--share**

Share the firewall rule to be used in all projects (by default, it is restricted to be used by the current project).

**--no-share**

Restrict use of the firewall rule to the current project

**--enable-rule**

Enable this rule (default is enabled)

**--disable-rule**

Disable this rule

**--source-firewall-group <source-firewall-group>**

Source firewall group (name or ID)

**--no-source-firewall-group**

No associated destination firewall group

**--destination-firewall-group <destination-firewall-group>**

Destination firewall group (name or ID)

**--no-destination-firewall-group**

No associated destination firewall group

**firewall-rule**

Firewall rule to set (name or ID)

This command is provided by the python-neutronclient plugin.

## firewall group rule show

Display firewall rule details

```
openstack firewall group rule show
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  <firewall-rule>
```

**-f <FORMATTER>, --format <FORMATTER>**

the output format, defaults to table

**-c COLUMN, --column COLUMN**

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, &lt;1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**firewall-rule**

Firewall rule to display (name or ID)

This command is provided by the python-neutronclient plugin.

**firewall group rule unset**

Unset firewall rule properties

```

openstack firewall group rule unset
  [--source-ip-address]
  [--destination-ip-address]
  [--source-port]
  [--destination-port]
  [--share]
  [--enable-rule]
  [--source-firewall-group]
  [--destination-firewall-group]
  <firewall-rule>

```

**--source-ip-address**

Source IP address or subnet

**--destination-ip-address**

Destination IP address or subnet

**--source-port**

Source port number or range(integer in [1, 65535] or range like 123:456)

**--destination-port**

Destination port number or range(integer in [1, 65535] or range like 123:456)

**--share**

Restrict use of the firewall rule to the current project

**--enable-rule**

Disable this rule

**--source-firewall-group**

Source firewall group (name or ID)

**--destination-firewall-group**

Destination firewall group (name or ID)

**firewall-rule**

Firewall rule to unset (name or ID)

This command is provided by the python-neutronclient plugin.

**network log**

A **network log** is a container to group security groups or ports for logging. Specified resources can be logged via these event (ALL, ACCEPT or DROP).

Network v2

**network loggable resources list**

List supported loggable resources

```
openstack network loggable resources list
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
  [--noindent]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--sort-column SORT_COLUMN]
  [--sort-ascending | --sort-descending]
  [--long]
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--quote** <QUOTE\_MODE>

when to include quotes, defaults to nonnumeric

**--noindent**

whether to disable indenting the JSON

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.



**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--sort-column** SORT\_COLUMN

specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated

**--sort-ascending**

sort the column(s) in ascending order

**--sort-descending**

sort the column(s) in descending order

**--long**

List additional fields in output

This command is provided by the python-neutronclient plugin.

**network log create**

Create a new network log

```
openstack network log create
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--description <description>]
  [--enable | --disable]
  [--project <project>]
  [--project-domain <project-domain>]
  [--event {ALL,ACCEPT,DROP}]
  --resource-type <resource-type>
  [--resource <resource>]
  [--target <target>]
  <name>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--description** <description>

Description of the network log

**--enable**

Enable this log

**--disable**

Disable this log (default is enabled)

**--project** <project>

Owners project (name or ID)

**--project-domain** <project-domain>

Domain the project belongs to (name or ID). This can be used in case collisions between project names exist.

**--event** {ALL,ACCEPT,DROP}

An event to store with log

**--resource-type** <resource-type>

Network log type(s). You can see supported type(s) with following command: \$ openstack network loggable resources list

**--resource** <resource>

Name or ID of resource (security group or firewall group) that used for logging. You can control for logging target combination with target option.

**--target** <target>

Port (name or ID) for logging. You can control for logging target combination with resource option.

**name**

Name for the network log

This command is provided by the python-neutronclient plugin.

## network log delete

Delete network log(s)

```
openstack network log delete <network-log> [<network-log> ...]
```

### network-log

Network log(s) to delete (name or ID)

This command is provided by the python-neutronclient plugin.

## network log list

List network logs

```
openstack network log list
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
  [--noindent]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--sort-column SORT_COLUMN]
  [--sort-ascending | --sort-descending]
  [--long]
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--quote** <QUOTE\_MODE>

when to include quotes, defaults to nonnumeric

**--noindent**

whether to disable indenting the JSON

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--sort-column** SORT\_COLUMN

specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated

**--sort-ascending**

sort the column(s) in ascending order

**--sort-descending**

sort the column(s) in descending order

**--long**

List additional fields in output

This command is provided by the python-neutronclient plugin.

## network log set

Set network log properties

```
openstack network log set
  [--description <description>]
  [--enable | --disable]
  [--name <name>]
  <network-log>
```

**--description <description>**

Description of the network log

**--enable**

Enable this log

**--disable**

Disable this log (default is enabled)

**--name <name>**

Name of the network log

**network-log**

Network log to set (name or ID)

This command is provided by the python-neutronclient plugin.

## network log show

Display network log details

```
openstack network log show
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  <network-log>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**network-log**

Network log to show (name or ID)

This command is provided by the python-neutronclient plugin.

## bgpvpn

A **bgpvpn** resource contains a set of parameters to define a BGP-based VPN. BGP-based IP VPNs networks are widely used in the industry especially for enterprises. The networking BGP VPN project aims at supporting inter-connection between L3VPNs and Neutron resources, i.e. Networks, Routers and Ports.

Network v2

### bgpvpn create

Create BGP VPN resource

```
openstack bgpvpn create
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--project <project>]
  [--project-domain <project-domain>]
  [--name <name>]
```

(continues on next page)

(continued from previous page)

```
[--route-target <route-target>]
[--import-target <import-target>]
[--export-target <export-target>]
[--route-distinguisher <route-distinguisher>]
[--vni VNI]
[--local-pref LOCAL_PREF]
[--type {12,13}]
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--project** <project>

Owners project (name or ID)

**--project-domain** <project-domain>

Domain the project belongs to (name or ID). This can be used in case collisions between project names exist.

**--name** <name>

Name of the BGP VPN

**--route-target** <route-target>

Add Route Target to import/export list (repeat option for multiple Route Targets)

**--import-target** <import-target>

Add Route Target to import list (repeat option for multiple Route Targets)

**--export-target** <export-target>

Add Route Target to export list (repeat option for multiple Route Targets)

**--route-distinguisher** <route-distinguisher>

Add Route Distinguisher to the list of Route Distinguishers from which a Route Distinguishers will be picked from to advertise a VPN route (repeat option for multiple Route Distinguishers)

**--vni** <VNI>

VXLAN Network Identifier to be used for this BGPVPN when a VXLAN encapsulation is used

**--local-pref** <LOCAL\_PREF>

Default BGP LOCAL\_PREF to use in route advertisements towards this BGPVPN.

**--type** <TYPE>

BGP VPN type selection between IP VPN (13) and Ethernet VPN (12) (default: 13)

This command is provided by the python-neutronclient plugin.

## bgpvpn delete

Delete BGP VPN resource(s)

```
openstack bgpvpn delete <bgpvpn> [<bgpvpn> ...]
```

### bgpvpn

BGP VPN(s) to delete (name or ID)

This command is provided by the python-neutronclient plugin.

## bgpvpn list

List BGP VPN resources

```
openstack bgpvpn list
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
  [--noindent]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--sort-column SORT_COLUMN]
  [--sort-ascending | --sort-descending]
  [--project <project>]
  [--project-domain <project-domain>]
  [--long]
  [--property <key=value>]
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--quote** <QUOTE\_MODE>

when to include quotes, defaults to nonnumeric

**--noindent**

whether to disable indenting the JSON

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--sort-column** SORT\_COLUMN

specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated

**--sort-ascending**

sort the column(s) in ascending order

**--sort-descending**

sort the column(s) in descending order

**--project** <project>

Owners project (name or ID)

**--project-domain** <project-domain>

Domain the project belongs to (name or ID). This can be used in case collisions between project names exist.

**--long**

List additional fields in output

**--property** <key=value>

Filter property to apply on returned BGP VPNs (repeat to filter on multiple properties)

This command is provided by the python-neutronclient plugin.

## bgpvpn set

Set BGP VPN properties

```
openstack bgpvpn set
  [--name <name>]
  [--route-target <route-target>]
  [--no-route-target]
  [--import-target <import-target>]
  [--no-import-target]
  [--export-target <export-target>]
  [--no-export-target]
  [--route-distinguisher <route-distinguisher>]
  [--no-route-distinguisher]
```

(continues on next page)



(continued from previous page)

```

[--vni VNI]
[--local-pref LOCAL_PREF]
<bgpvpn>

```

**--name** <name>

Name of the BGP VPN

**--route-target** <route-target>

Add Route Target to import/export list (repeat option for multiple Route Targets)

**--no-route-target**

Empty route target list

**--import-target** <import-target>

Add Route Target to import list (repeat option for multiple Route Targets)

**--no-import-target**

Empty import route target list

**--export-target** <export-target>

Add Route Target to export list (repeat option for multiple Route Targets)

**--no-export-target**

Empty export route target list

**--route-distinguisher** <route-distinguisher>

Add Route Distinguisher to the list of Route Distinguishers from which a Route Distinguishers will be picked from to advertise a VPN route (repeat option for multiple Route Distinguishers)

**--no-route-distinguisher**

Empty route distinguisher list

**--vni** <VNI>

VXLAN Network Identifier to be used for this BGPVPN when a VXLAN encapsulation is used

**--local-pref** <LOCAL\_PREF>

Default BGP LOCAL\_PREF to use in route advertisementstowards this BGPVPN.

**bgpvpn**

BGP VPN to update (name or ID)

This command is provided by the python-neutronclient plugin.

**bgpvpn show**

Show information of a given BGP VPN

```

openstack bgpvpn show
[-f {json,shell,table,value,yaml}]
[-c COLUMN]
[--noindent]
[--prefix PREFIX]

```

(continues on next page)

(continued from previous page)

```

[--max-width <integer>]
[--fit-width]
[--print-empty]
<bgvpn>

```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**bgvpn**

BGP VPN to display (name or ID)

This command is provided by the python-neutronclient plugin.

## bgvpn unset

Unset BGP VPN properties

```

openstack bgvpn unset
  [--route-target <route-target>]
  [--all-route-target]
  [--import-target <import-target>]
  [--all-import-target]
  [--export-target <export-target>]
  [--all-export-target]
  [--route-distinguisher <route-distinguisher>]
  [--all-route-distinguisher]
  [--vni VNI]
  [--local-pref LOCAL_PREF]
  <bgvpn>

```

- route-target** <route-target>  
Remove Route Target from import/export list (repeat option for multiple Route Targets)
  - all-route-target**  
Empty route target list
  - import-target** <import-target>  
Remove Route Target from import list (repeat option for multiple Route Targets)
  - all-import-target**  
Empty import route target list
  - export-target** <export-target>  
Remove Route Target from export list (repeat option for multiple Route Targets)
  - all-export-target**  
Empty export route target list
  - route-distinguisher** <route-distinguisher>  
Remove Route Distinguisher from the list of Route Distinguishers from which a Route Distinguishers will be picked from to advertise a VPN route (repeat option for multiple Route Distinguishers)
  - all-route-distinguisher**  
Empty route distinguisher list
  - vni** <VNI>  
VXLAN Network Identifier to be used for this BGPVPN when a VXLAN encapsulation is used
  - local-pref** <LOCAL\_PREF>  
Default BGP LOCAL\_PREF to use in route advertisementstowards this BGPVPN.
- bgpvpn**  
BGP VPN to update (name or ID)

This command is provided by the python-neutronclient plugin.

## bgpvpn network association create

Create a BGP VPN network association

```
openstack bgpvpn network association create
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--project <project>]
  [--project-domain <project-domain>]
  <bgpvpn>
  <network>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--project** <project>

Owners project (name or ID)

**--project-domain** <project-domain>

Domain the project belongs to (name or ID). This can be used in case collisions between project names exist.

**bgpvpn**

BGP VPN to apply the network association (name or ID)

**network**

Network to associate the BGP VPN (name or ID)

This command is provided by the python-neutronclient plugin.

### bgpvpn network association delete

Delete a BGP VPN network association(s) for a given BGP VPN

```
openstack bgpvpn network association delete
  <network
  association
  ID>
  [<network association ID> ...]
  <bgpvpn>
```

**network** association ID

Network association ID(s) to remove

**bgpvpn**

BGP VPN the network association belongs to (name or ID)

This command is provided by the python-neutronclient plugin.

**bgpvpn network association list**

List BGP VPN network associations for a given BGP VPN

```
openstack bgpvpn network association list
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
  [--noindent]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--sort-column SORT_COLUMN]
  [--sort-ascending | --sort-descending]
  [--long]
  [--property <key=value>]
  <bgpvpn>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--quote** <QUOTE\_MODE>

when to include quotes, defaults to nonnumeric

**--noindent**

whether to disable indenting the JSON

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--sort-column** SORT\_COLUMN

specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated

**--sort-ascending**

sort the column(s) in ascending order

**--sort-descending**

sort the column(s) in descending order

**--long**

List additional fields in output

**--property <key=value>**

Filter property to apply on returned BGP VPNs (repeat to filter on multiple properties)

**bgpvpn**

BGP VPN listed associations belong to (name or ID)

This command is provided by the python-neutronclient plugin.

**bgpvpn network association show**

Show information of a given BGP VPN network association

```
openstack bgpvpn network association show
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  <network
  association
  ID>
  <bgpvpn>
```

**-f <FORMATTER>, --format <FORMATTER>**

the output format, defaults to table

**-c COLUMN, --column COLUMN**

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix <PREFIX>**

add a prefix to all variable names

**--max-width <integer>**

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**network** association ID

Network association ID to look up

**bgpvpn**

BGP VPN the association belongs to (name or ID)

This command is provided by the python-neutronclient plugin.

### bgpvpn router association create

Create a BGP VPN router association

```
openstack bgpvpn router association create
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--project <project>]
  [--project-domain <project-domain>]
  [--advertise_extra_routes | --no-advertise_extra_routes]
  <bgpvpn>
  <router>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--project** <project>

Owners project (name or ID)

**--project-domain** <project-domain>

Domain the project belongs to (name or ID). This can be used in case collisions between project names exist.

**--advertise\_extra\_routes**

Routes will be advertised to the BGP VPN (default)

**--no-advertise\_extra\_routes**

Routes from the router will not be advertised to the BGP VPN

**bgpvpn**

BGP VPN to apply the router association (name or ID)

**router**

Router to associate the BGP VPN (name or ID)

This command is provided by the python-neutronclient plugin.

### bgpvpn router association delete

Delete a BGP VPN router association(s) for a given BGP VPN

```
openstack bgpvpn router association delete
  <router
  association
  ID>
  [<router association ID> ...]
  <bgpvpn>
```

**router** association ID

Router association ID(s) to remove

**bgpvpn**

BGP VPN the router association belongs to (name or ID)

This command is provided by the python-neutronclient plugin.

### bgpvpn router association list

List BGP VPN router associations for a given BGP VPN

```
openstack bgpvpn router association list
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
  [--noindent]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--sort-column SORT_COLUMN]
  [--sort-ascending | --sort-descending]
```

(continues on next page)



(continued from previous page)

```

[--long]
[--property <key=value>]
<bgvpn>

```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--quote** <QUOTE\_MODE>

when to include quotes, defaults to nonnumeric

**--noindent**

whether to disable indenting the JSON

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--sort-column** SORT\_COLUMN

specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated

**--sort-ascending**

sort the column(s) in ascending order

**--sort-descending**

sort the column(s) in descending order

**--long**

List additional fields in output

**--property** <key=value>

Filter property to apply on returned BGP VPNs (repeat to filter on multiple properties)

**bgvpn**

BGP VPN listed associations belong to (name or ID)

This command is provided by the python-neutronclient plugin.

## bgpvpn router association set

Set BGP VPN router association properties

```
openstack bgpvpn router association set
  [--advertise_extra_routes | --no-advertise_extra_routes]
  <router
  association
  ID>
  <bgpvpn>
```

### --advertise\_extra\_routes

Routes will be advertised to the BGP VPN

### --no-advertise\_extra\_routes

Routes from the router will not be advertised to the BGP VPN

**router** association ID

Router association ID to update

### bgpvpn

BGP VPN the router association belongs to (name or ID)

This command is provided by the python-neutronclient plugin.

## bgpvpn router association show

Show information of a given BGP VPN router association

```
openstack bgpvpn router association show
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  <router
  association
  ID>
  <bgpvpn>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**router** association ID

Router association ID to look up

**bgpvpn**

BGP VPN the association belongs to (name or ID)

This command is provided by the python-neutronclient plugin.

### bgpvpn router association unset

Unset BGP VPN router association properties

```
openstack bgpvpn router association unset
  [--advertise_extra_routes | --no-advertise_extra_routes]
  <router
  association
  ID>
  <bgpvpn>
```

**--advertise\_extra\_routes**

Routes from the router will not be advertised to the BGP VPN

**--no-advertise\_extra\_routes**

Routes will be advertised to the BGP VPN

**router** association ID

Router association ID to update

**bgpvpn**

BGP VPN the router association belongs to (name or ID)

This command is provided by the python-neutronclient plugin.

## bgpvpn port association create

Create a BGP VPN port association

```
openstack bgpvpn port association create
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--project <project>]
  [--project-domain <project-domain>]
  [--advertise-fixed-ips | --no-advertise-fixed-ips]
  [--prefix-route prefix=<cidr>[,local_pref=<integer>]]
  [--bgpvpn-route bgpvpn=<BGP VPN ID or name>[,local_pref=<integer>]]
  <bgpvpn>
  <port>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--project** <project>

Owners project (name or ID)

**--project-domain** <project-domain>

Domain the project belongs to (name or ID). This can be used in case collisions between project names exist.

**--advertise-fixed-ips**

Fixed IPs of the port will be advertised to the BGP VPN (default)

**--no-advertise-fixed-ips**

Fixed IPs of the port will not be advertised to the BGP VPN

**--prefix-route prefix=<cidr>[,local\_pref=<integer>]**

Add prefix route in CIDR notation. Optionally, can control the value of the BGP LOCAL\_PREF of the routes that will be advertised (repeat option for multiple prefix routes)

**--bgpvpn-route bgpvpn=<BGP VPN ID or name>[,local\_pref=<integer>]**

Add BGP VPN route for route leaking. Optionally, can control the value of the BGP LOCAL\_PREF of the routes that will be advertised (repeat option for multiple BGP VPN routes)

**bgpvpn**

BGP VPN to apply the port association (name or ID)

**port**

Port to associate the BGP VPN (name or ID)

This command is provided by the python-neutronclient plugin.

**bgpvpn port association delete**

Delete a BGP VPN port association(s) for a given BGP VPN

```
openstack bgpvpn port association delete
  <port
  association
  ID>
  [<port association ID> ...]
  <bgpvpn>
```

**port association ID**

Port association ID(s) to remove

**bgpvpn**

BGP VPN the port association belongs to (name or ID)

This command is provided by the python-neutronclient plugin.

**bgpvpn port association list**

List BGP VPN port associations for a given BGP VPN

```
openstack bgpvpn port association list
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
  [--noindent]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--sort-column SORT_COLUMN]
```

(continues on next page)

(continued from previous page)

```
[--sort-ascending | --sort-descending]
[--long]
[--property <key=value>]
<bgpvpn>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--quote** <QUOTE\_MODE>

when to include quotes, defaults to nonnumeric

**--noindent**

whether to disable indenting the JSON

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--sort-column** SORT\_COLUMN

specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated

**--sort-ascending**

sort the column(s) in ascending order

**--sort-descending**

sort the column(s) in descending order

**--long**

List additional fields in output

**--property** <key=value>

Filter property to apply on returned BGP VPNs (repeat to filter on multiple properties)

**bgpvpn**

BGP VPN listed associations belong to (name or ID)

This command is provided by the python-neutronclient plugin.

## bgpvpn port association set

Set BGP VPN port association properties

```

openstack bgpvpn port association set
  [--advertise-fixed-ips | --no-advertise-fixed-ips]
  [--prefix-route prefix=<cidr>[,local_pref=<integer>]]
  [--bgpvpn-route bgpvpn=<BGP VPN ID or name>[,local_pref=<integer>]]
  [--no-prefix-route]
  [--no-bgpvpn-route]
  <port
  association
  ID>
  <bgpvpn>

```

### --advertise-fixed-ips

Fixed IPs of the port will be advertised to the BGP VPN

### --no-advertise-fixed-ips

Fixed IPs of the port will not be advertised to the BGP VPN

### --prefix-route prefix=<cidr>[,local\_pref=<integer>]

Add prefix route in CIDR notation. Optionally, can control the value of the BGP LOCAL\_PREF of the routes that will be advertised (repeat option for multiple prefix routes)

### --bgpvpn-route bgpvpn=<BGP VPN ID or name>[,local\_pref=<integer>]

Add BGP VPN route for route leaking. Optionally, can control the value of the BGP LOCAL\_PREF of the routes that will be advertised (repeat option for multiple BGP VPN routes)

### --no-prefix-route

Empty prefix route list

### --no-bgpvpn-route

Empty BGP VPN route list

**port** association ID

Port association ID to update

### bgpvpn

BGP VPN the port association belongs to (name or ID)

This command is provided by the python-neutronclient plugin.

## bgpvpn port association show

Show information of a given BGP VPN port association

```

openstack bgpvpn port association show
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]

```

(continues on next page)

(continued from previous page)

```

[--max-width <integer>]
[--fit-width]
[--print-empty]
<port
association
ID>
<bgpvpn>

```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**port** association ID

Port association ID to look up

**bgpvpn**

BGP VPN the association belongs to (name or ID)

This command is provided by the python-neutronclient plugin.

## bgpvpn port association unset

Unset BGP VPN port association properties

```

openstack bgpvpn port association unset
[--advertise-fixed-ips | --no-advertise-fixed-ips]
[--prefix-route <cidr>]
[--bgpvpn-route <BGP VPN ID or name>]
[--all-prefix-routes]
[--all-bgpvpn-routes]
<port
association

```

(continues on next page)



(continued from previous page)

```
ID>
<bgpvpn>
```

**--advertise-fixed-ips**

Fixed IPs of the port will not be advertised to the BGP VPN

**--no-advertise-fixed-ips**

Fixed IPs of the port will be advertised to the BGP VPN

**--prefix-route <cidr>**

Remove prefix route in CIDR notation (repeat option for multiple prefix routes)

**--bgpvpn-route <BGP VPN ID or name>**

Remove BGP VPN route (repeat option for multiple BGP VPN routes)

**--all-prefix-routes**

Empty prefix route list

**--all-bgpvpn-routes**

Empty BGP VPN route list

**port** association ID

Port association ID to update

**bgpvpn**

BGP VPN the port association belongs to (name or ID)

This command is provided by the python-neutronclient plugin.

**networking sfc**

**Service Function Chaining** is a mechanism for overriding the basic destination based forwarding that is typical of IP networks. Service Function Chains consist of an ordered sequence of Service Functions (SFs). SFs are virtual machines (or potentially physical devices) that perform a network function such as firewall, content cache, packet inspection, or any other function that requires processing of packets in a flow from point A to point B even though the SFs are not literally between point A and B from a routing table perspective.

Network v2

**sfc flow classifier create**

Create a flow classifier

```
openstack sfc flow classifier create
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
```

(continues on next page)

(continued from previous page)

```

[--print-empty]
[--description <description>]
[--protocol <protocol>]
[--ethertype {IPv4,IPv6}]
[--source-port <min-port>:<max-port>]
[--destination-port <min-port>:<max-port>]
[--source-ip-prefix <source-ip-prefix>]
[--destination-ip-prefix <destination-ip-prefix>]
[--logical-source-port <logical-source-port>]
[--logical-destination-port <logical-destination-port>]
[--l7-parameters L7_PARAMETERS]
<name>

```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--description** <description>

Description for the flow classifier

**--protocol** <protocol>

IP protocol name. Protocol name should be as per IANA standard.

**--ethertype** {IPv4,IPv6}

L2 ethertype, default is IPv4

**--source-port** <min-port>:<max-port>

Source protocol port (allowed range [1,65535]). Must be specified as a:b, where a=min-port and b=max-port) in the allowed range.

**--destination-port** <min-port>:<max-port>

Destination protocol port (allowed range [1,65535]). Must be specified as a:b, where a=min-port and b=max-port) in the allowed range.

- source-ip-prefix** <source-ip-prefix>  
Source IP address in CIDR notation
- destination-ip-prefix** <destination-ip-prefix>  
Destination IP address in CIDR notation
- logical-source-port** <logical-source-port>  
Neutron source port (name or ID)
- logical-destination-port** <logical-destination-port>  
Neutron destination port (name or ID)
- l7-parameters** <L7\_PARAMETERS>  
Dictionary of L7 parameters. Currently, no value is supported for this option.

**name**

Name of the flow classifier

This command is provided by the python-neutronclient plugin.

**sfc flow classifier delete**

Delete a given flow classifier

```
openstack sfc flow classifier delete
  <flow-classifier>
  [<flow-classifier> ...]
```

**flow-classifier**

Flow classifier(s) to delete (name or ID)

This command is provided by the python-neutronclient plugin.

**sfc flow classifier list**

List flow classifiers

```
openstack sfc flow classifier list
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
  [--noindent]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--sort-column SORT_COLUMN]
  [--sort-ascending | --sort-descending]
  [--long]
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

- c COLUMN, --column COLUMN**  
specify the column(s) to include, can be repeated to show multiple columns
- quote <QUOTE\_MODE>**  
when to include quotes, defaults to nonnumeric
- noindent**  
whether to disable indenting the JSON
- max-width <integer>**  
Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.
- fit-width**  
Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable
- print-empty**  
Print empty table if there is no data to show.
- sort-column SORT\_COLUMN**  
specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated
- sort-ascending**  
sort the column(s) in ascending order
- sort-descending**  
sort the column(s) in descending order
- long**  
List additional fields in output

This command is provided by the python-neutronclient plugin.

### sfc flow classifier set

Set flow classifier properties

```
openstack sfc flow classifier set
  [--name <name>]
  [--description <description>]
  <flow-classifier>
```

- name <name>**  
Name of the flow classifier
  - description <description>**  
Description for the flow classifier
- flow-classifier**  
Flow classifier to modify (name or ID)

This command is provided by the python-neutronclient plugin.

## sfc flow classifier show

Display flow classifier details

```

openstack sfc flow classifier show
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  <flow-classifier>

```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**flow-classifier**

Flow classifier to display (name or ID)

This command is provided by the python-neutronclient plugin.

## sfc port chain create

Create a port chain

```

openstack sfc port chain create
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]

```

(continues on next page)

(continued from previous page)

```
[--fit-width]
[--print-empty]
[--description <description>]
[--flow-classifier <flow-classifier>]
[--chain-parameters correlation=<correlation-type>,symmetric=<boolean>]
--port-pair-group <port-pair-group>
<name>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--description** <description>

Description for the port chain

**--flow-classifier** <flow-classifier>

Add flow classifier (name or ID). This option can be repeated.

**--chain-parameters** correlation=<correlation-type>,symmetric=<boolean>

Dictionary of chain parameters. Supports correlation=(mpls|nsh) (default is mpls) and symmetric=(true|false).

**--port-pair-group** <port-pair-group>

Add port pair group (name or ID). This option can be repeated.

**name**

Name of the port chain

This command is provided by the python-neutronclient plugin.

## sfc port chain delete

Delete a given port chain

```
openstack sfc port chain delete <port-chain> [<port-chain> ...]
```

### port-chain

Port chain(s) to delete (name or ID)

This command is provided by the python-neutronclient plugin.

## sfc port chain list

List port chains

```
openstack sfc port chain list
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
  [--noindent]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--sort-column SORT_COLUMN]
  [--sort-ascending | --sort-descending]
  [--long]
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--quote** <QUOTE\_MODE>

when to include quotes, defaults to nonnumeric

**--noindent**

whether to disable indenting the JSON

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--sort-column** SORT\_COLUMN

specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated

**--sort-ascending**

sort the column(s) in ascending order

**--sort-descending**

sort the column(s) in descending order

**--long**

List additional fields in output

This command is provided by the python-neutronclient plugin.

## sfc port chain set

Set port chain properties

```
openstack sfc port chain set
  [--name <name>]
  [--description <description>]
  [--flow-classifier <flow-classifier>]
  [--no-flow-classifier]
  [--port-pair-group <port-pair-group>]
  [--no-port-pair-group]
  <port-chain>
```

**--name <name>**

Name of the port chain

**--description <description>**

Description for the port chain

**--flow-classifier <flow-classifier>**

Add flow classifier (name or ID). This option can be repeated.

**--no-flow-classifier**

Remove associated flow classifiers from the port chain

**--port-pair-group <port-pair-group>**

Add port pair group (name or ID). Current port pair groups order is kept, the added port pair group will be placed at the end of the port chain. This option can be repeated.

**--no-port-pair-group**

Remove associated port pair groups from the port chain. At least one port-pair-group must be specified together.

**port-chain**

Port chain to modify (name or ID)

This command is provided by the python-neutronclient plugin.



## sfc port chain show

Display port chain details

```

openstack sfc port chain show
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  <port-chain>

```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**port-chain**

Port chain to display (name or ID)

This command is provided by the python-neutronclient plugin.

## sfc port chain unset

Unset port chain properties

```

openstack sfc port chain unset
  [--flow-classifier <flow-classifier> | --all-flow-classifier]
  [--port-pair-group <port-pair-group>]
  <port-chain>

```

**--flow-classifier** <flow-classifier>

Remove flow classifier(s) from the port chain (name or ID). This option can be repeated.

**--all-flow-classifier**

Remove all flow classifiers from the port chain

**--port-pair-group** <port-pair-group>

Remove port pair group(s) from the port chain (name or ID). This option can be repeated.

**port-chain**

Port chain to unset (name or ID)

This command is provided by the python-neutronclient plugin.

## sfc port pair create

Create a port pair

```
openstack sfc port pair create
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--description <description>]
  [--service-function-parameters correlation=<correlation-type>,weight=
  ↪<weight>]
  --ingress <ingress>
  --egress <egress>
  <name>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--description** <description>

Description for the port pair

**--service-function-parameters** correlation=<correlation-type>,weight=<weight>

Dictionary of service function parameters. Currently, correlation=(None|mpls|nsh) and weight are supported. Weight is an integer that influences the selection of a port pair within a port pair group for a flow. The higher the weight, the more flows will hash to the port pair. The default weight is 1.

**--ingress** <ingress>

Ingress neutron port (name or ID)

**--egress** <egress>

Egress neutron port (name or ID)

**name**

Name of the port pair

This command is provided by the python-neutronclient plugin.

**sfc port pair delete**

Delete a given port pair

```
openstack sfc port pair delete <port-pair> [<port-pair> ...]
```

**port-pair**

Port pair(s) to delete (name or ID)

This command is provided by the python-neutronclient plugin.

**sfc port pair list**

List port pairs

```
openstack sfc port pair list
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
  [--noindent]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--sort-column SORT_COLUMN]
  [--sort-ascending | --sort-descending]
  [--long]
```

- f** <FORMATTER>, **--format** <FORMATTER>  
the output format, defaults to table
- c** COLUMN, **--column** COLUMN  
specify the column(s) to include, can be repeated to show multiple columns
- quote** <QUOTE\_MODE>  
when to include quotes, defaults to nonnumeric
- noindent**  
whether to disable indenting the JSON
- max-width** <integer>  
Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.
- fit-width**  
Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable
- print-empty**  
Print empty table if there is no data to show.
- sort-column** SORT\_COLUMN  
specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated
- sort-ascending**  
sort the column(s) in ascending order
- sort-descending**  
sort the column(s) in descending order
- long**  
List additional fields in output

This command is provided by the python-neutronclient plugin.

## sfc port pair set

Set port pair properties

```
openstack sfc port pair set  
  [--name <name>]  
  [--description <description>]  
  <port-pair>
```

- name** <name>  
Name of the port pair
- description** <description>  
Description for the port pair

**port-pair**

Port pair to modify (name or ID)

This command is provided by the python-neutronclient plugin.

**sfc port pair show**

Display port pair details

```
openstack sfc port pair show
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  <port-pair>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**port-pair**

Port pair to display (name or ID)

This command is provided by the python-neutronclient plugin.

## sfc port pair group create

Create a port pair group

```
openstack sfc port pair group create
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--description <description>]
  [--port-pair <port-pair>]
  [--enable-tap | --disable-tap]
  [--port-pair-group-parameters lb-fields=<lb-fields>]
  <name>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--description** <description>

Description for the port pair group

**--port-pair** <port-pair>

Port pair (name or ID). This option can be repeated.

**--enable-tap**

Port pairs of this port pair group are deployed as passive tap service function

**--disable-tap**

Port pairs of this port pair group are deployed as I3 service function (default)

**--port-pair-group-parameters** lb-fields=<lb-fields>

Dictionary of port pair group parameters. Currently only one parameter lb-fields is supported. <lb-fields> is a & separated list of load-balancing fields.

**name**

Name of the port pair group

This command is provided by the python-neutronclient plugin.

### sfc port pair group delete

Delete a given port pair group

```
openstack sfc port pair group delete
  <port-pair-group>
  [<port-pair-group> ...]
```

**port-pair-group**

Port pair group(s) to delete (name or ID)

This command is provided by the python-neutronclient plugin.

### sfc port pair group list

List port pair group

```
openstack sfc port pair group list
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
  [--noindent]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--sort-column SORT_COLUMN]
  [--sort-ascending | --sort-descending]
  [--long]
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--quote** <QUOTE\_MODE>

when to include quotes, defaults to nonnumeric

**--noindent**

whether to disable indenting the JSON

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--sort-column** SORT\_COLUMN

specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated

**--sort-ascending**

sort the column(s) in ascending order

**--sort-descending**

sort the column(s) in descending order

**--long**

List additional fields in output

This command is provided by the python-neutronclient plugin.

## sfc port pair group set

Set port pair group properties

```
openstack sfc port pair group set
  [--name <name>]
  [--description <description>]
  [--port-pair <port-pair>]
  [--no-port-pair]
  <port-pair-group>
```

**--name** <name>

Name of the port pair group

**--description** <description>

Description for the port pair group

**--port-pair** <port-pair>

Port pair (name or ID). This option can be repeated.

**--no-port-pair**

Remove all port pair from port pair group

**port-pair-group**

Port pair group to modify (name or ID)

This command is provided by the python-neutronclient plugin.



## sfc port pair group show

Display port pair group details

```

openstack sfc port pair group show
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  <port-pair-group>

```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**port-pair-group**

Port pair group to display (name or ID)

This command is provided by the python-neutronclient plugin.

## sfc port pair group unset

Unset port pairs from port pair group

```

openstack sfc port pair group unset
  [--port-pair <port-pair> | --all-port-pair]
  <port-pair-group>

```

**--port-pair** <port-pair>

Remove port pair(s) from the port pair group (name or ID). This option can be repeated.

**--all-port-pair**

Remove all port pairs from the port pair group

**port-pair-group**

Port pair group to unset (name or ID)

This command is provided by the python-neutronclient plugin.

**sfc service graph create**

Create a service graph.

```
openstack sfc service graph create
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--description DESCRIPTION]
  --branching-point SRC_CHAIN
  :DST_CHAIN_1,DST_CHAIN_2,DST_CHAIN_N
  <name>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--description** <DESCRIPTION>

Description for the service graph.

**--branching-point** SRC\_CHAIN:DST\_CHAIN\_1,DST\_CHAIN\_2,DST\_CHAIN\_N

Service graph branching point: the key is the source Port Chain while the value is a list of destination Port Chains. This option can be repeated.

**name**

Name of the service graph.

This command is provided by the python-neutronclient plugin.

**sfc service graph delete**

Delete a given service graph.

```
openstack sfc service graph delete
  <service-graph>
  [<service-graph> ...]
```

**service-graph**

ID or name of the service graph(s) to delete.

This command is provided by the python-neutronclient plugin.

**sfc service graph list**

List service graphs

```
openstack sfc service graph list
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
  [--noindent]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--sort-column SORT_COLUMN]
  [--sort-ascending | --sort-descending]
  [--long]
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--quote** <QUOTE\_MODE>

when to include quotes, defaults to nonnumeric

**--noindent**

whether to disable indenting the JSON

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--sort-column** SORT\_COLUMN

specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated

**--sort-ascending**

sort the column(s) in ascending order

**--sort-descending**

sort the column(s) in descending order

**--long**

List additional fields in output

This command is provided by the python-neutronclient plugin.

## sfc service graph set

Set service graph properties

```
openstack sfc service graph set
  [--name <name>]
  [--description <description>]
  <service-graph>
```

**--name** <name>

Name of the service graph

**--description** <description>

Description for the service graph

**service-graph**

Service graph to modify (name or ID)

This command is provided by the python-neutronclient plugin.

## sfc service graph show

Show information of a given service graph.

```
openstack sfc service graph show
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
```

(continues on next page)

(continued from previous page)

```

[--fit-width]
[--print-empty]
<service-graph>

```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**service-graph**

ID or name of the service graph to display.

This command is provided by the python-neutronclient plugin.

## network onboard subnets

**network onboard subnets** enables a subnet to be adopted or onboarded into an existing subnet pool. The CIDR of the subnet is checked for uniqueness across any applicable address scopes and all subnets allocated from the target subnet pool. Once onboarded, the subnet CIDR is added to the prefix list of the subnet pool and the subnet appears as though it has been allocated from the subnet pool. The subnet also begins participating in the applicable address scope if the subnet pool belongs to one.

Network v2

## network onboard subnets

Onboard network subnets into a subnet pool

```

openstack network onboard subnets <network> <subnetpool>

```

**network**

Onboard all subnets associated with this network

## subnetpool

Target subnet pool for onboarding subnets

This command is provided by the python-neutronclient plugin.

## VPN Endpoint Group

The **Endpoint Group** is used to configure multiple local and remote subnets in vpnservice object.

Network v2

### vpn endpoint group create

Create an endpoint group

```
openstack vpn endpoint group create
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--description <description>]
  --type TYPE
  --value ENDPOINTS
  [--project <project>]
  [--project-domain <project-domain>]
  <name>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--description** <description>

Description for the endpoint group

**--type** <TYPE>

Type of endpoints in group (e.g. subnet, cidr)

**--value** <ENDPOINTS>

Endpoint(s) for the group. Must all be of the same type. (value) option can be repeated

**--project** <project>

Owners project (name or ID)

**--project-domain** <project-domain>

Domain the project belongs to (name or ID). This can be used in case collisions between project names exist.

**name**

Name for the endpoint group

This command is provided by the python-neutronclient plugin.

### vpn endpoint group delete

Delete endpoint group(s)

```
openstack vpn endpoint group delete
  <endpoint-group>
  [<endpoint-group> ...]
```

**endpoint-group**

Endpoint group(s) to delete (name or ID)

This command is provided by the python-neutronclient plugin.

### vpn endpoint group list

List endpoint groups that belong to a given project

```
openstack vpn endpoint group list
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
  [--noindent]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--sort-column SORT_COLUMN]
  [--sort-ascending | --sort-descending]
  [--long]
```

- f** <FORMATTER>, **--format** <FORMATTER>  
the output format, defaults to table
- c** COLUMN, **--column** COLUMN  
specify the column(s) to include, can be repeated to show multiple columns
- quote** <QUOTE\_MODE>  
when to include quotes, defaults to nonnumeric
- noindent**  
whether to disable indenting the JSON
- max-width** <integer>  
Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.
- fit-width**  
Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable
- print-empty**  
Print empty table if there is no data to show.
- sort-column** SORT\_COLUMN  
specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated
- sort-ascending**  
sort the column(s) in ascending order
- sort-descending**  
sort the column(s) in descending order
- long**  
List additional fields in output

This command is provided by the python-neutronclient plugin.

## vpn endpoint group set

Set endpoint group properties

```
openstack vpn endpoint group set
  [--description <description>]
  [--name <name>]
  <endpoint-group>
```

- description** <description>  
Description for the endpoint group
- name** <name>  
Set a name for the endpoint group



**endpoint-group**

Endpoint group to set (name or ID)

This command is provided by the python-neutronclient plugin.

**vpn endpoint group show**

Display endpoint group details

```
openstack vpn endpoint group show
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  <endpoint-group>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**endpoint-group**

Endpoint group to display (name or ID)

This command is provided by the python-neutronclient plugin.

## VPN IKE Policy

The **IKE Policy** is used for phases one and two negotiation of the VPN connection. You can specify both the authentication and encryption algorithms for connections.

Network v2

### vpn ike policy create

Create an IKE policy

```
openstack vpn ike policy create
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--description <description>]
  [--auth-algorithm {sha1,sha256,sha384,sha512}]
  [--encryption-algorithm {aes-128,3des,aes-192,aes-256}]
  [--phase1-negotiation-mode {main,aggressive}]
  [--ike-version {v1,v2}]
  [--pfs {group5,group2,group14}]
  [--lifetime units=UNITS,value=VALUE]
  [--project <project>]
  [--project-domain <project-domain>]
  <name>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--description** <description>  
Description of the IKE policy

**--auth-algorithm** <AUTH\_ALGORITHM>  
Authentication algorithm

**--encryption-algorithm** <ENCRYPTION\_ALGORITHM>  
Encryption algorithm

**--phase1-negotiation-mode** <PHASE1\_NEGOTIATION\_MODE>  
IKE Phase1 negotiation mode

**--ike-version** <IKE\_VERSION>  
IKE version for the policy

**--pfs** <PFS>  
Perfect Forward Secrecy

**--lifetime** units=UNITS,value=VALUE  
IKE lifetime attributes. units-seconds, default:seconds. value-non negative integer, default:3600.

**--project** <project>  
Owners project (name or ID)

**--project-domain** <project-domain>  
Domain the project belongs to (name or ID). This can be used in case collisions between project names exist.

**name**  
Name of the IKE policy

This command is provided by the python-neutronclient plugin.

### vpn ike policy delete

Delete IKE policy (policies)

```
openstack vpn ike policy delete <ike-policy> [<ike-policy> ...]
```

#### ike-policy

IKE policy to delete (name or ID)

This command is provided by the python-neutronclient plugin.

### vpn ike policy list

List IKE policies that belong to a given project

```
openstack vpn ike policy list
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
```

(continues on next page)

(continued from previous page)

```
[--noindent]
[--max-width <integer>]
[--fit-width]
[--print-empty]
[--sort-column SORT_COLUMN]
[--sort-ascending | --sort-descending]
[--long]
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--quote** <QUOTE\_MODE>

when to include quotes, defaults to nonnumeric

**--noindent**

whether to disable indenting the JSON

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--sort-column** SORT\_COLUMN

specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated

**--sort-ascending**

sort the column(s) in ascending order

**--sort-descending**

sort the column(s) in descending order

**--long**

List additional fields in output

This command is provided by the python-neutronclient plugin.

## vpn ike policy set

Set IKE policy properties

```

openstack vpn ike policy set
  [--description <description>]
  [--auth-algorithm {sha1,sha256,sha384,sha512}]
  [--encryption-algorithm {aes-128,3des,aes-192,aes-256}]
  [--phase1-negotiation-mode {main,aggressive}]
  [--ike-version {v1,v2}]
  [--pfs {group5,group2,group14}]
  [--lifetime units=UNITS,value=VALUE]
  [--name <name>]
  <ike-policy>

```

**--description** <description>

Description of the IKE policy

**--auth-algorithm** <AUTH\_ALGORITHM>

Authentication algorithm

**--encryption-algorithm** <ENCRYPTION\_ALGORITHM>

Encryption algorithm

**--phase1-negotiation-mode** <PHASE1\_NEGOTIATION\_MODE>

IKE Phase1 negotiation mode

**--ike-version** <IKE\_VERSION>

IKE version for the policy

**--pfs** <PFS>

Perfect Forward Secrecy

**--lifetime** units=UNITS,value=VALUE

IKE lifetime attributes. units-seconds, default:seconds. value-non negative integer, default:3600.

**--name** <name>

Name of the IKE policy

### ike-policy

IKE policy to set (name or ID)

This command is provided by the python-neutronclient plugin.

## vpn ike policy show

Display IKE policy details

```

openstack vpn ike policy show
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]

```

(continues on next page)

(continued from previous page)

```

[--prefix PREFIX]
[--max-width <integer>]
[--fit-width]
[--print-empty]
<ike-policy>

```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**ike-policy**

IKE policy to display (name or ID)

This command is provided by the python-neutronclient plugin.

## VPN IPsec Policy

The **IPsec Policy** specifies the authentication and encryption algorithms and encapsulation mode to use for the established VPN connection.

Network v2

### vpn ipsec policy create

Create an IPsec policy

```

openstack vpn ipsec policy create
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]

```

(continues on next page)

(continued from previous page)

```

[--fit-width]
[--print-empty]
[--description <description>]
[--auth-algorithm {sha1,sha256,sha384,sha512}]
[--encapsulation-mode {tunnel,transport}]
[--encryption-algorithm {3des,aes-128,aes-192,aes-256}]
[--lifetime units=UNITS,value=VALUE]
[--pfs {group2,group5,group14}]
[--transform-protocol {esp,ah,ah-esp}]
[--project <project>]
[--project-domain <project-domain>]
<name>

```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--description** <description>

Description of the IPsec policy

**--auth-algorithm** <AUTH\_ALGORITHM>

Authentication algorithm for IPsec policy

**--encapsulation-mode** <ENCAPSULATION\_MODE>

Encapsulation mode for IPsec policy

**--encryption-algorithm** <ENCRYPTION\_ALGORITHM>

Encryption algorithm for IPsec policy

**--lifetime** units=UNITS,value=VALUE

IPsec lifetime attributes. units-seconds, default:seconds. value-non negative integer, default:3600.

**--pfs** <PFS>

Perfect Forward Secrecy for IPsec policy

**--transform-protocol** <TRANSFORM\_PROTOCOL>

Transform protocol for IPsec policy

**--project** <project>

Owners project (name or ID)

**--project-domain** <project-domain>

Domain the project belongs to (name or ID). This can be used in case collisions between project names exist.

**name**

Name of the IPsec policy

This command is provided by the python-neutronclient plugin.

### vpn ipsec policy delete

Delete IPsec policy(policies)

```
openstack vpn ipsec policy delete <ipsec-policy> [<ipsec-policy> ...]
```

**ipsec-policy**

ipsec policy to delete (name or ID)

This command is provided by the python-neutronclient plugin.

### vpn ipsec policy list

List IPsec policies that belong to a given project

```
openstack vpn ipsec policy list
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
  [--noindent]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--sort-column SORT_COLUMN]
  [--sort-ascending | --sort-descending]
  [--long]
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--quote** <QUOTE\_MODE>

when to include quotes, defaults to nonnumeric



**--noindent**

whether to disable indenting the JSON

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--sort-column** SORT\_COLUMN

specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated

**--sort-ascending**

sort the column(s) in ascending order

**--sort-descending**

sort the column(s) in descending order

**--long**

List additional fields in output

This command is provided by the python-neutronclient plugin.

**vpn ipsec policy set**

Set IPsec policy properties

```
openstack vpn ipsec policy set
  [--description <description>]
  [--auth-algorithm {sha1,sha256,sha384,sha512}]
  [--encapsulation-mode {tunnel,transport}]
  [--encryption-algorithm {3des,aes-128,aes-192,aes-256}]
  [--lifetime units=UNITS,value=VALUE]
  [--pfs {group2,group5,group14}]
  [--transform-protocol {esp,ah,ah-esp}]
  [--name <name>]
  <ipsec-policy>
```

**--description** <description>

Description of the IPsec policy

**--auth-algorithm** <AUTH\_ALGORITHM>

Authentication algorithm for IPsec policy

**--encapsulation-mode** <ENCAPSULATION\_MODE>

Encapsulation mode for IPsec policy

- encryption-algorithm** <ENCRYPTION\_ALGORITHM>  
Encryption algorithm for IPsec policy
- lifetime** units=UNITS, value=VALUE  
IPsec lifetime attributes. units-seconds, default:seconds. value-non negative integer, default:3600.
- pfs** <PFS>  
Perfect Forward Secrecy for IPsec policy
- transform-protocol** <TRANSFORM\_PROTOCOL>  
Transform protocol for IPsec policy
- name** <name>  
Name of the IPsec policy

### **ipsec-policy**

IPsec policy to set (name or ID)

This command is provided by the python-neutronclient plugin.

### **vpn ipsec policy show**

Display IPsec policy details

```
openstack vpn ipsec policy show
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  <ipsec-policy>
```

- f** <FORMATTER>, **--format** <FORMATTER>  
the output format, defaults to table
- c** COLUMN, **--column** COLUMN  
specify the column(s) to include, can be repeated to show multiple columns
- noindent**  
whether to disable indenting the JSON
- prefix** <PREFIX>  
add a prefix to all variable names
- max-width** <integer>  
Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.
- fit-width**  
Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**ipsec-policy**

IPsec policy to display (name or ID)

This command is provided by the python-neutronclient plugin.

**VPN IPsec Site Connection**

Creates a site-to-site **IPsec Site Connection** for a VPN service.

Network v2

**vpn ipsec site connection create**

Create an IPsec site connection

```
openstack vpn ipsec site connection create
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--description <description>]
  [--dpd action=ACTION,interval=INTERVAL,timeout=TIMEOUT]
  [--mtu MTU]
  [--initiator {bi-directional,response-only}]
  [--peer-cidr PEER_CIDRS | --local-endpoint-group LOCAL_ENDPOINT_GROUP]
  [--peer-endpoint-group PEER_ENDPOINT_GROUP]
  [--enable | --disable]
  [--local-id LOCAL_ID]
  --peer-id PEER_ID
  --peer-address PEER_ADDRESS
  --psk PSK
  --vpnservice VPNSERVICE
  --ikepolicy IKEPOLICY
  --ipsecpolicy IPSECPOLICY
  [--project <project>]
  [--project-domain <project-domain>]
  <name>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--description** <description>

Description for the connection

**--dpd** action=ACTION,interval=INTERVAL,timeout=TIMEOUT

Ipssec connection Dead Peer Detection attributes. action=hold,clear,disabled,restart,restart-by-peer. interval and timeout are non negative integers. interval should be less than timeout value. action, default:hold interval, default:30, timeout, default:120.

**--mtu** <MTU>

MTU size for the connection

**--initiator** <INITIATOR>

Initiator state

**--peer-cidr** <PEER\_CIDRS>

Remote subnet(s) in CIDR format. Cannot be specified when using endpoint groups. Only applicable, if subnet provided for VPN service.

**--local-endpoint-group** <LOCAL\_ENDPOINT\_GROUP>

Local endpoint group (name or ID) with subnet(s) for IPsec connection

**--peer-endpoint-group** <PEER\_ENDPOINT\_GROUP>

Peer endpoint group (name or ID) with CIDR(s) for IPsec connection

**--enable**

Enable IPsec site connection

**--disable**

Disable IPsec site connection

**--local-id** <LOCAL\_ID>

An ID to be used instead of the external IP address for a virtual router

**--peer-id** <PEER\_ID>

Peer router identity for authentication. Can be IPv4/IPv6 address, e-mail address, key id, or FQDN

**--peer-address** <PEER\_ADDRESS>

Peer gateway public IPv4/IPv6 address or FQDN

- psk** <PSK>  
Pre-shared key string.
- vpnservice** VPNSERVICE  
VPN service instance associated with this connection (name or ID)
- ikepolicy** IKEPOLICY  
IKE policy associated with this connection (name or ID)
- ipsecpolicy** IPSECPOLICY  
IPsec policy associated with this connection (name or ID)
- project** <project>  
Owners project (name or ID)
- project-domain** <project-domain>  
Domain the project belongs to (name or ID). This can be used in case collisions between project names exist.
- name**  
Set friendly name for the connection

This command is provided by the python-neutronclient plugin.

### vpn ipsec site connection delete

Delete IPsec site connection(s)

```
openstack vpn ipsec site connection delete
  <ipsec-site-connection>
  [<ipsec-site-connection> ...]
```

#### ipsec-site-connection

IPsec site connection to delete (name or ID)

This command is provided by the python-neutronclient plugin.

### vpn ipsec site connection list

List IPsec site connections that belong to a given project

```
openstack vpn ipsec site connection list
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
  [--noindent]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--sort-column SORT_COLUMN]
  [--sort-ascending | --sort-descending]
  [--long]
```

- f** <FORMATTER>, **--format** <FORMATTER>  
the output format, defaults to table
- c** COLUMN, **--column** COLUMN  
specify the column(s) to include, can be repeated to show multiple columns
- quote** <QUOTE\_MODE>  
when to include quotes, defaults to nonnumeric
- noindent**  
whether to disable indenting the JSON
- max-width** <integer>  
Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.
- fit-width**  
Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable
- print-empty**  
Print empty table if there is no data to show.
- sort-column** SORT\_COLUMN  
specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated
- sort-ascending**  
sort the column(s) in ascending order
- sort-descending**  
sort the column(s) in descending order
- long**  
List additional fields in output

This command is provided by the python-neutronclient plugin.

## vpn ipsec site connection set

Set IPsec site connection properties

```
openstack vpn ipsec site connection set
  [--description <description>]
  [--dpd action=ACTION,interval=INTERVAL,timeout=TIMEOUT]
  [--mtu MTU]
  [--initiator {bi-directional,response-only}]
  [--peer-cidr PEER_CIDRS | --local-endpoint-group LOCAL_ENDPOINT_GROUP]
  [--peer-endpoint-group PEER_ENDPOINT_GROUP]
  [--enable | --disable]
  [--local-id LOCAL_ID]
  [--peer-id PEER_ID]
  [--peer-address PEER_ADDRESS]
```

(continues on next page)

(continued from previous page)

```
[--name <name>]
<ipsec-site-connection>
```

**--description** <description>

Description for the connection

**--dpd** action=ACTION, interval=INTERVAL, timeout=TIMEOUT

Ipssec connection Dead Peer Detection attributes. action=hold,clear,disabled,restart,restart-by-peer. interval and timeout are non negative integers. interval should be less than timeout value. action, default:hold interval, default:30, timeout, default:120.

**--mtu** <MTU>

MTU size for the connection

**--initiator** <INITIATOR>

Initiator state

**--peer-cidr** <PEER\_CIDRS>

Remote subnet(s) in CIDR format. Cannot be specified when using endpoint groups. Only applicable, if subnet provided for VPN service.

**--local-endpoint-group** <LOCAL\_ENDPOINT\_GROUP>

Local endpoint group (name or ID) with subnet(s) for IPsec connection

**--peer-endpoint-group** <PEER\_ENDPOINT\_GROUP>

Peer endpoint group (name or ID) with CIDR(s) for IPsec connection

**--enable**

Enable IPsec site connection

**--disable**

Disable IPsec site connection

**--local-id** <LOCAL\_ID>

An ID to be used instead of the external IP address for a virtual router

**--peer-id** <PEER\_ID>

Peer router identity for authentication. Can be IPv4/IPv6 address, e-mail address, key id, or FQDN

**--peer-address** <PEER\_ADDRESS>

Peer gateway public IPv4/IPv6 address or FQDN

**--name** <name>

Set friendly name for the connection

**ipsec-site-connection**

IPsec site connection to set (name or ID)

This command is provided by the python-neutronclient plugin.

## vpn ipsec site connection show

Show information of a given IPsec site connection

```
openstack vpn ipsec site connection show
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  <ipsec-site-connection>
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**ipsec-site-connection**

IPsec site connection to display (name or ID)

This command is provided by the python-neutronclient plugin.

## VPN Service

The **VPN Service** is associated with a router. After you create the service, it can contain multiple VPN connections.

Network v2



## vpn service create

Create an VPN service

```

openstack vpn service create
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--description <description>]
  [--subnet <subnet>]
  [--flavor <flavor>]
  [--enable | --disable]
  --router ROUTER
  [--project <project>]
  [--project-domain <project-domain>]
  <name>

```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

**-c** COLUMN, **--column** COLUMN

specify the column(s) to include, can be repeated to show multiple columns

**--noindent**

whether to disable indenting the JSON

**--prefix** <PREFIX>

add a prefix to all variable names

**--max-width** <integer>

Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**

Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**

Print empty table if there is no data to show.

**--description** <description>

Description for the VPN service

**--subnet** <subnet>

Local private subnet (name or ID)

**--flavor** <flavor>

Flavor for the VPN service (name or ID)

**--enable**

Enable VPN service

**--disable**

Disable VPN service

**--router** ROUTER

Router for the VPN service (name or ID)

**--project** <project>

Owners project (name or ID)

**--project-domain** <project-domain>

Domain the project belongs to (name or ID). This can be used in case collisions between project names exist.

**name**

Name for the VPN service

This command is provided by the python-neutronclient plugin.

## vpn service delete

Delete VPN service(s)

```
openstack vpn service delete <vpn-service> [<vpn-service> ...]
```

**vpn-service**

VPN service to delete (name or ID)

This command is provided by the python-neutronclient plugin.

## vpn service list

List VPN services that belong to a given project

```
openstack vpn service list
  [-f {csv,json,table,value,yaml}]
  [-c COLUMN]
  [--quote {all,minimal,none,nonnumeric}]
  [--noindent]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  [--sort-column SORT_COLUMN]
  [--sort-ascending | --sort-descending]
  [--long]
```

**-f** <FORMATTER>, **--format** <FORMATTER>

the output format, defaults to table

- c COLUMN, --column COLUMN**  
specify the column(s) to include, can be repeated to show multiple columns
- quote <QUOTE\_MODE>**  
when to include quotes, defaults to nonnumeric
- noindent**  
whether to disable indenting the JSON
- max-width <integer>**  
Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.
- fit-width**  
Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable
- print-empty**  
Print empty table if there is no data to show.
- sort-column SORT\_COLUMN**  
specify the column(s) to sort the data (columns specified first have a priority, non-existing columns are ignored), can be repeated
- sort-ascending**  
sort the column(s) in ascending order
- sort-descending**  
sort the column(s) in descending order
- long**  
List additional fields in output

This command is provided by the python-neutronclient plugin.

## vpn service set

Set VPN service properties

```
openstack vpn service set
  [--description <description>]
  [--subnet <subnet>]
  [--flavor <flavor>]
  [--enable | --disable]
  [--name <name>]
  <vpn-service>
```

- description <description>**  
Description for the VPN service
- subnet <subnet>**  
Local private subnet (name or ID)

**--flavor** <flavor>  
Flavor for the VPN service (name or ID)

**--enable**  
Enable VPN service

**--disable**  
Disable VPN service

**--name** <name>  
Name for the VPN service

**vpn-service**  
VPN service to modify (name or ID)

This command is provided by the python-neutronclient plugin.

### vpn service show

Display VPN service details

```
openstack vpn service show
  [-f {json,shell,table,value,yaml}]
  [-c COLUMN]
  [--noindent]
  [--prefix PREFIX]
  [--max-width <integer>]
  [--fit-width]
  [--print-empty]
  <vpn-service>
```

**-f** <FORMATTER>, **--format** <FORMATTER>  
the output format, defaults to table

**-c** COLUMN, **--column** COLUMN  
specify the column(s) to include, can be repeated to show multiple columns

**--noindent**  
whether to disable indenting the JSON

**--prefix** <PREFIX>  
add a prefix to all variable names

**--max-width** <integer>  
Maximum display width, <1 to disable. You can also use the CLIFF\_MAX\_TERM\_WIDTH environment variable, but the parameter takes precedence.

**--fit-width**  
Fit the table to the display width. Implied if max-width greater than 0. Set the environment variable CLIFF\_FIT\_WIDTH=1 to always enable

**--print-empty**  
Print empty table if there is no data to show.

## vpn-service

VPN service to display (name or ID)

This command is provided by the python-neutronclient plugin.

### 1.1.2 neutron CLI

#### Warning

neutron CLI is removed. Use openstack CLI instead. See [openstack CLI command list](#) and *its extensions for advanced networking services*. The command mapping from neutron CLI to openstack CLI is available [here](#).

## 1.2 neutronclient Python API

### 1.2.1 Basic Usage

First create a client instance using a keystoneauth Session. For more information on this keystoneauth API, see [Using Sessions](#).

```

from keystoneauth1 import identity
from keystoneauth1 import session
from neutronclient.v2_0 import client
username='username'
password='password'
project_name='demo'
project_domain_id='default'
user_domain_id='default'
auth_url='http://auth.example.com:5000/v3'
auth = identity.Password(auth_url=auth_url,
                        username=username,
                        password=password,
                        project_name=project_name,
                        project_domain_id=project_domain_id,
                        user_domain_id=user_domain_id)
sess = session.Session(auth=auth)
neutron = client.Client(session=sess)

```

If you are using Identity v2.0 API (DEPRECATED), create an auth plugin using the appropriate parameters and `keystoneauth1.identity` will handle Identity API version discovery. Then you can create a Session and a Neutronclient just like the previous example.

```

auth = identity.Password(auth_url=auth_url,
                        username=username,
                        password=password,
                        project_name=project_name)
# create a Session and a Neutronclient

```

Now you can call various methods on the client instance.

```
network = {'name': 'mynetwork', 'admin_state_up': True}
neutron.create_network({'network':network})
networks = neutron.list_networks(name='mynetwork')
print networks
network_id = networks['networks'][0]['id']
neutron.delete_network(network_id)
```

Alternatively, you can create a client instance using an auth token and a service endpoint URL directly.

```
from neutronclient.v2_0 import client
neutron = client.Client(endpoint_url='http://192.168.206.130:9696/',
                        token='d3f9226f27774f338019aa2611112ef6')
```

You can get X-Openstack-Request-Id as request\_ids from the result.

```
network = {'name': 'mynetwork', 'admin_state_up': True}
neutron.create_network({'network':network})
networks = neutron.list_networks(name='mynetwork')
print networks.request_ids
# -> ['req-978a0160-7ab0-44f0-8a93-08e9a4e785fa']
```

## CONTRIBUTOR GUIDE

In the *Contributor Guide*, you will find information on neutronclients lower level programming details or APIs as well as the transition to OpenStack client.

### 2.1 Contributor Guide

In the Contributor Guide, you will find information on neutronclients lower level programming details or APIs as well as the transition to OpenStack client.

#### 2.1.1 Transition to OpenStack Client

This document details the transition roadmap for moving the neutron clients OpenStack Networking API support, both the Python library and the `neutron` command-line interface (CLI), to the [OpenStack Client \(OSC\)](#) and the [OpenStack Python SDK](#). This transition is being guided by the [Deprecate individual CLIs in favour of OSC](#) OpenStack spec. See the [Neutron RFE](#), [OSC neutron support etherpad](#) and details below for the overall progress of this transition.

#### Overview

This transition will result in the neutron clients `neutron` CLI being deprecated and then eventually removed. The `neutron` CLI will be replaced by OSC's networking support available via the `openstack` CLI. This is similar to the deprecation and removal process for the [keystone clients keystone](#) CLI. The neutron clients Python library wont be deprecated. It will be available along side the networking support provided by the OpenStack Python SDK.

Users of the neutron clients command extensions will need to transition to the [OSC plugin system](#) before the `neutron` CLI is removed. Such users will maintain their OSC plugin commands within their own project and will be responsible for deprecating and removing their `neutron` CLI extension.

## Transition Steps

1. **Done:** OSC adds OpenStack Python SDK as a dependency. See the following patch set: <https://review.opendev.org/#/c/138745/>
2. **Done:** OSC switches its networking support for the `network` command object to use the OpenStack Python SDK instead of the neutron clients Python library. See the following patch set: <https://review.opendev.org/#/c/253348/>
3. **Done:** OSC removes its python-neutronclient dependency. See the following patch set: <https://review.opendev.org/#/c/255545/>
4. **In Progress:** OpenStack Python SDK releases version 1.0 to guarantee backwards compatibility of its networking support and OSC updates its dependencies to include OpenStack Python SDK version 1.0 or later. See the following blueprint: <https://blueprints.launchpad.net/python-openstackclient/+spec/network-command-sdk-support>
5. **Done:** OSC switches its networking support for the `ip floating`, `ip floating pool`, `ip fixed`, `security group`, and `security group rule` command objects to use the OpenStack Python SDK instead of the nova clients Python library when neutron is enabled. When nova network is enabled, then the nova clients Python library will continue to be used. See the following OSC bugs:
  - **Done** Floating IP CRUD
  - **Done** Port CRUD
  - **Done** Security Group CRUD
  - **Done** Security Group Rule CRUD
6. **Done** OSC continues enhancing its networking support. At this point and when applicable, enhancements to the `neutron` CLI must also be made to the `openstack` CLI and possibly the OpenStack Python SDK. Users of the neutron clients command extensions should start their transition to the OSC plugin system. See the developer guide section below for more information on this step.
7. **Done** Deprecate the `neutron` CLI. Running the CLI after it has been `deprecated` will issue a warning message: `neutron CLI is deprecated and will be removed in the Z cycle`. Use `openstack CLI` instead. In addition, no new features will be added to the CLI, though fixes to the CLI will be assessed on a case by case basis.
8. **Done** Remove the `neutron` CLI after two deprecation cycles once the criteria below have been met.
  - The networking support provide by the `openstack` CLI is functionally equivalent to the `neutron` CLI and it contains sufficient functional and unit test coverage.
  - `Neutron Stadium` projects, Neutron documentation and `DevStack` use `openstack` CLI instead of `neutron` CLI.
  - Most users of the neutron clients command extensions have transitioned to the OSC plugin system and use the `openstack` CLI instead of the `neutron` CLI.



## Developer Guide

The `neutron` CLI tool is now removed and all new CLI changes should be done in the `OpenStackClient` (OSC) and, if needed, also in the `OpenStack SDK`.

### Where does my CLI belong?

If you are developing an API in any of the [neutron repos](#) the client-side support must be generally located in either the `openstackclient` or `neutronclient` repos. Whether the actual code goes into one or the other repo it depends on the nature of the feature, its maturity level, and/or the depth of feedback required during the development.

The table below provides an idea of what goes where. Generally speaking, we consider Core anything that is L2 and L3 related or that it has been located in the `neutron` repo for quite sometime, e.g. QoS or Metering, or that it is available in each `neutron` deployment irrespective of its configuration (e.g. auto-allocated-topology). Any client feature that falls into this categorization will need to be contributed in OSC. Any other that does not, will need to go into `neutronclient`, assuming that its server-side is located in a `neutron` controlled repo. This is a general guideline, when in doubt, please reach out to a member of the `neutron` core team for clarifications.

Networking Commands	OSC Plugin	OpenStack Project for openstack Commands
Core	No	<code>python-openstackclient</code>
Extension (i.e. <code>neutron stadium</code> )	Yes	<code>python-neutronclient</code> ( <code>neutronclient/osc/v2/&lt;extension&gt;</code> )
Other	Yes	Applicable project owning networking resource

When a repo stops being under `neutron` governance, its client-side counterpart will have to go through deprecation. Bear in mind that for grandfathered extensions like `FWaaS v1`, `VPNaaS`, and `LBaaS v1`, this is not required as the `neutronclient` is already deprecated on its own.

### Which Python library do I change?

OpenStack Project for openstack Commands	Python Library to Change
<code>python-openstackclient</code>	<code>openstacksdk</code>
Other	Applicable project owning network resource

**Important:** The actual name of the command object and/or action in OSC may differ from those used by `neutron` in order to follow the OSC command structure and to avoid name conflicts. The `network` prefix must be used to avoid name conflicts if the command object name is highly likely to have an ambiguous meaning. Developers should get new command objects and actions approved by the OSC team before proceeding with the implementation.

The Core group includes network resources that provide core `neutron` project features (e.g. `network`, `subnet`, `port`, etc.) and not advanced features in the `neutron` project (e.g. `trunk`, etc.) or advanced services in separate projects (`FWaaS`, `LBaaS`, `VPNaaS`, `dynamic routing`, etc.). The Other group applies projects other than the core `neutron` project. Contact the `neutron` PTL or core team with questions on network resource classification.

When adding or updating an `openstack` networking command to `python-openstackclient`, changes may first be required to the `OpenStack Python SDK` to support the underlying networking resource object, properties and/or actions. Once the `OpenStack Python SDK` changes are merged, the related OSC changes

can be merged. The OSC changes may require an update to the OSC openstacksdk version in the `requirements.txt` file.

When adding an openstack networking command to `python-openstackclient`, you can optionally propose an `OSC command spec` which documents the new command interface before proceeding with the implementation.

Users of the neutron clients command extensions must adopt the `OSC plugin` system for this transition. Such users will maintain their OSC plugin within their own project and should follow the guidance in the table above to determine which command to change.

## Developer References

- See `OSC neutron support etherpad` to determine if an openstack command is in progress.
- See `OSC command list` to determine if an openstack command exists.
- See `OSC command spec list` to determine if an openstack command spec exists.
- See `OSC plugin command list` to determine if an openstack plugin command exists.
- See `OSC command structure` to determine the current openstack command objects, plugin objects and actions.
- See `OSC human interface guide` for guidance on creating new OSC command interfaces.
- See `OSC plugin` for information on the OSC plugin system to be used for neutron CLI extensions.
- Create an OSC blueprint: <https://blueprints.launchpad.net/python-openstackclient/>
- Report an OSC bug: <https://bugs.launchpad.net/python-openstackclient/+filebug>
- Report an OpenStack Python SDK bug: <https://bugs.launchpad.net/python-openstacksdk/+filebug>

### Note

neutron CLI has been deprecated from Ocata release. We do not add, change and drop any existing commands any more. We only accept changes on OSC plugin, neutronclient python bindings and bug fixes on the deprecated CLI (`neutron` command).

---

**CHAPTER  
THREE**

---

**HISTORY**

Release notes is available at <http://docs.openstack.org/releasenotes/python-neutronclient/>.